
IR-USB Serial Command Reference:

Note: All commands sent to the IR-USB must be terminated by a carriage return or carriage return and linefeed, which is shown in this document as " C_R " and " L_F ". Any parameters shown in square brackets "[]" are optional. Parameters are separated from commands and from each other by a space " ". Spaces within commands are shown in this document as " S_P ". All commands are case insensitive, meaning any combination of upper/lower case characters are accepted.

The USB connection appears on the PC as a virtual serial COM Port. In order to communicate with the IR-USB, the PC running a terminal program (such as HyperTerminal) must have the following serial communication settings:

Baud: 9600
Data Bits: 8
Parity: None
Stop Bits: 1
Handshaking: None

A Command:

Description: - Transmit ambient temperature in Deg C and Deg F.

Syntax: $A^{C_R}[^{L_F}]$

Parts: None. There are no parameters for this command.

Remarks: Ambient temperature should not exceed 158 °F or damage to the electronics may result.

Example:

Assuming ambient temperature is 75.9 °F, the following is shown on the PC (terminal) screen after typing "A" and pressing the <Enter> key:

A
SNS AMB = 24.3, 75.9 C_R L_F >

C Command:

Description: - Transmit temperature in Deg C.

Syntax: $C^{C_R}[^{L_F}]$

Parts: None. There are no parameters for this command.

Remarks: None.

Example:

Assuming probe temperature is 125 °C, the following is shown on the PC (terminal) screen after typing "C" and pressing the <Enter> key:

C
125 C_R L_F >

F Command:

Description: - Transmit temperature in Deg F.

Syntax: $F^{C_R [L_F]}$

Parts: None. There are no parameters for this command.

Remarks: None.

Example:

Assuming probe temperature is 257 °F, the following is shown on the PC (terminal) screen after typing "F" and pressing the <Enter> key:

F
257^{C_R L_F}>

E Command:

Description: - Set/Transmit emissivity.

Syntax: $E^{[S_P \text{ EMISSIVITY}] C_R [L_F]}$

Parts:

EMISSIVITY (OPTIONAL)

Specifies the emissivity. Valid range of values is 0.10 to 1.00.

Remarks: None.

Example:

Assuming emissivity is 1.00, the following is shown on the PC (terminal) screen after typing "E" and pressing the <Enter> key:

E
E = 1.00^{C_R L_F}>

To set the emissivity to 0.50, type the following and press the <Enter> key:

E 0.50
This will then display:
E = 0.50^{C_R L_F}>

ENQ Command:

Description: - Transmit model number and firmware version.

Syntax: ENQ $C_R [L_F]$

Parts: None. There are no parameters for this command.

Remarks:

The firmware version is a six-digit number

Example:

The following is shown on the PC (terminal) screen after typing "ENQ" and pressing the <Enter> key:

```
IRUSB2  $C_R [L_F]$   
100716  $C_R [L_F]$ >
```

IFILTER Command:

Description: - Set/Transmit IIR filter period.

Syntax: IFILTER[S_P PERIOD] $C_R [L_F]$

Parts:

PERIOD (OPTIONAL)

Specifies the period to be used by the IIR filter. Valid range of values is 0 to 255. A value of 0 will disable this filter. The default value is 9.

Remarks:

IIR (Infinite Impulse Response) filter is used to filter raw analog to digital converter readings for high frequencies and impulse noise.

Example:

The following is shown on the PC (terminal) screen after typing "IFILTER" and pressing the <Enter> key:

```
IFILTER  
I = 9  $C_R [L_F]$ >
```

The following is shown on the PC (terminal) screen after typing "IFILTER 50" and pressing the <Enter> key:

```
IFILTER  
I = 50  $C_R [L_F]$ >
```

MFILTER Command:

Description: - Set/Transmit Moving Average filter order.

Syntax: **MFILTER**[^S_P **ORDER**]^C_R [^L_F]

Parts:

ORDER (OPTIONAL)

Specifies the order value to be used by the Moving Average filter. Valid range of values is 0 to 63. A value of 0 will disable this filter. The default value is 4.

Remarks:

MA (Moving Average) filter used to filter temperature values (Deg F or Deg C) to smooth out low frequency variations in temperature.

Example:

The following is shown on the PC (terminal) screen after typing "MFILTER" and pressing the <Enter> key:

```
MFILTER  
M = 4CR LF>
```

The following is shown on the PC (terminal) screen after typing "MFILTER 10" and pressing the <Enter> key:

```
MFILTER  
M = 10CR LF>
```

PA Command:

Description: - Transmit Process and Ambient temperature in Degrees Fahrenheit, without units.

Syntax: **PA**^C_R [^L_F]

Parts: None. There are no parameters for this command.

Remarks: Ambient temperature should not exceed 158 °F or damage to the electronics may result.

Example:

Assuming probe temperature is 257 °F and the ambient temperature is 105 °F, the following is shown on the PC (terminal) screen after typing "PA" and pressing the <Enter> key:

```
257, 105.0CR LF>
```
